

SZCZECIN UNIVERSITY OF TECHNOLOGY



**Automatic Defect Detection and Identification Processor
ADDIP**

USER MANUAL
(modified May, 6th 2009)

May, 2007

Index

ADD	6
ANNCLASSIFIER	7
ANNCLS	8
ANNTHRESHOLD	10
ATH	11
BDILATE	12
BERODE	13
CALCFEAT	14
CF	15
CHDIR	16
CROPIMAGE	17
CUTROI	18
DETECTROI	19
DILATE	20
DM	21
ERODE	22
ETH	23
EXIT	24
FASTMEDIAN	25
FASTMEDIANMP	26
FFTFILT	27
FILLHOLES	28
GENINDEXEDIMG	29
GETIMSIZE	30
GETMATRIXELEMENT	31
GTH	32
HIST	33
IMADD	34
IMCLOSE	35
IMMULTI	36
IMNORMALIZE	37
IMPORTBINARYMATRIX	38
IMREAD	39

IMSHOW	40
IMSUB	41
IMWRITE	42
INDEX	43
INVERSE	44
ISEECOMMAND	45
ISEEGETFILE	46
ISEEGETROI	47
ISEEPORT	48
ITH	49
IQIDET	50
IQIMAX	51
LENGTHAREA	52
MATRIXREAD	53
MATRIXWRITE	54
MEDIAN	55
MULT_ADD	56
NEIGHB	57
NEURAL	58
NORMALIZE	59
NORM_RADIO	60
NTH	61
OTH	62
OUTLINE	63
PREWITT	64
READTIFF	65
ROBERTS	66
ROTATEIMAGE	67
SAUVOLA	68
SAVEFEAT	69
SAVESTAT	70
SAVEIMAGEM	71
SOBEL	72
STATISTIC	73
STH	74

STHAD	75
THREADS	76
WELDANGLE	77
WRITETIFF	78
WSKPRECLASSIFIER	79
WSKCLASSIFIER	80

Introduction

Automatic Defect Detection and Identification Processor (ADDIP) is a collection of advanced image processing algorithms dedicated for automatic radiograph analysis. The ADDIP was created as a programming environment for quick and easy testing newly developed algorithms for defect identification and recognition. Generally, ADDIP is an interpreter of a scripting language that currently supports over 50 commands that can operate on various data types (images, matrices etc). The one of the advantages of ADDIP is that the code of the processor is completely independent from the codes of the implemented (in it) functions. Thanks to this a new function can be added to the processor within very short time and existing function can be easily transferred to an another project with minimal changes in their code.

Here are some basic rules of correct writing a script files:

1. Only one instruction per line is allowed
2. Comments can't be in the same line as commands
3. Particular line can't be longer than 256 chars
4. Use double backslash in the file paths
5. A line should not begin with "white chars" (spaces, tabs...)

Supported datatypes:

- IMAGE
- STRING
- MATRIX
- NUMBER

Known Bugs:

- using variable names the same as the function names may crash the program
- sometimes ADDIP do not load external DLLs if script is run by double click

ADD							
Syntax:							
Parameters:							
Description:	Adds two numbers.						
References:							
List of used functions:	none						
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2007.03.20	Date of last update:	2007.03.20	Version:	1.0
History of updates:	none						
Script syntax:	<i>result = add(number1,number2);</i>						
Script parameters:	<i>number1</i> – number to add <i>number2</i> – number to add <i>result</i> – result						
Example script:	<i>output = add(4, 5);</i> <i>% result is saved to res.txt file</i> <i>matrixwrite(output,'c:\\res.txt');</i>						
Remarks:	none						

ANNclassifier							
Syntax:							
Parameters:							
Description:	Performs Artificial Neural Network (ANN) based flaw's classification. Operates on tables of features (input vectors arranged in column wise order). Output table consists of classification vectors arranged also in column wise order. Position of the biggest value in output vector determine the class number.						
References:	<p>[1] Gang Wang, T. Warren Liao: "Automatic identification of different types of welding defects in radiographic images", NDT&E International 35 (2002), p. 519-528</p> <p>[2] Shaun W. Lawson, Graham A. Parker: "Intelligent segmentation of industrial radiographic images using neural networks", Proc. SPIE Vol. 2347, p. 245-255, Machine Vision Applications, Architectures, and Systems Integration III, 1994</p>						
List of used functions:							
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2007.08.1	Date of last update:	2007.08.1	Version:	1.0
History of updates:	none						
Script syntax:	<i>output</i> = ANNclassifier (<i>input</i> , 'filename');						
Script parameters:	<i>input</i> - input table of features <i>output</i> - output table of features 'filename' - name of the file where the ANN structure is stored						
Example script:	<pre> chdir('C:\addip\radiograms'); % view of input vector stored in inpvector.txt file: % 2 % 4 % [0,0,1,1; % 0,1,0,1] % reading the features table from file in = matrixread('inpvector.txt'); % performing classification process (XOR function) out = ANNclassifier(in,'ffnet_xor_NN_classifier_10_5_2.ann'); % view of output vector stored in outvector.txt file % 2 % 4 % [0.998627, 0.001739, 0.001430, 0.998425; % 0.002549, 0.999784, 0.999815, 0.002774] % ^ ^ ^ ^ % class1 class2 class2 class1 % writing results to file matrixwrite(out,'outvector.txt');</pre>						
Remarks:	none						

ANNCLS							
Syntax:							
Parameters:							
Description:	Performs Artificial Neural Network (ANN) based flaw's classification. Operates on normalized tables of features (input vectors arranged in row wise order). Output table consists of classification vectors arranged in column wise order.						
References:	<p>[1] Gang Wang, T. Warren Liao: "Automatic identification of different types of welding defects in radiographic images", NDT&E International 35 (2002), p. 519-528</p> <p>[2] Shaun W. Lawson, Graham A. Parker: "Intelligent segmentation of industrial radiographic images using neural networks", Proc. SPIE Vol. 2347, p. 245-255, Machine Vision Applications, Architectures, and Systems Integration III, 1994</p>						
List of used functions:							
File name (C-code):				DLL – library name:	ANNcls.dll		
Developed by:	PSz	Date of development:	2007.08.1	Date of last update:	2007.10.2	Version:	1.2
History of updates:	none						
Script syntax:	[out, disc] = ANNcls(tab, 'filename', num);						
Script parameters:	<p>tab - input table of features</p> <p>'filename' - name of the *.ann file where the ANN structure is stored</p> <p>num - number of defects</p> <p>out - table of ANN outputs</p> <p>disc - classes vector</p>						
Example script:	<pre> chdir('C:\addip\radiograms'); % read the image original = imread('Flaw_mix_02.tif'); cut = cutroi(original,600,2000,500,1100); % and display it on the screen (without scaling) handle1 = imshow('original',cut,0); % median filtering med = fastmedian(cut,0,71,71); % subtracting filtered image from original image sub = imsub(cut,med); handle2 = imshow('sub',sub,1); % iterative thresholding th = ith(sub,0.85); % removing small dots out_med = fastmedian(th,0,7,7); % recognizing flaws indexed_image = index(out_med); [num,tab] = calcfeat (cut,indexed_image,out_med,30,100000); savefeat(tab,num,'features.txt'); im_f = genindeximg(cut,out_med,tab,num,1); % displaying result handle3 = imshow('ith',out_med,1); handle4 = imshow('numbered',im_f,1); % performing classification process (requires ANNcls.dll) [out, disc] = ANNcls(tab,'ffnet_round_elong_NN_classifier_4_3_2.ann',num); % writing results to file matrixwrite(out,'outvector.txt'); matrixwrite(disc,'outvectorDisc.txt'); % % exemplary view of 'outvector.txt' (2 classes applied): % [0.990233, 0.990364, 0.990365, 0.990379, 0.989409; % 0.008268, 0.008172, 0.008170, 0.008162, 0.008881] % ^ ^ ^ ^ ^ % defect1 defect2 defect3 defect4 defect5 % % exemplary view of 'outvectorDisc.txt' (1-round defect, 2-long defect): % [1.000000, 1.000000, 1.000000, 1.000000, 1.000000] % ^ ^ ^ ^ ^ % class of class of class of class of class of % defect1 defect2 defect3 defect4 defect5 </pre>						

Remarks:	none
----------	------

ANNthreshold							
Syntax:							
Parameters:							
Description:	Performs flaw's detection algorithm using Artificial Neural Network (ANN) technique. The filtering window moves from pixel to pixel over an input image. Acquired data (intensities of pixels) are given as an input of previously trained nonlinear neural filter. For each position of the window one point of output image is estimated. Operates on gray scale images. Output image has the same size as input.						
References:	Shaun W. Lawson, Graham A. Parker: "Intelligent segmentation of industrial radiographic images using neural networks", Proc. SPIE Vol. 2347, p. 245-255, Machine Vision Applications, Architectures, and Systems Integration III, 1994						
List of used functions:							
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2007.04.12	Date of last update:	2007.04.12	Version:	1.0
History of updates:	none						
Script syntax:	<code>output = ANNthreshold (input, 'filename');</code>						
Script parameters:	<code>input</code> - input image <code>output</code> - output image <code>'filename'</code> - name of the file where the ANN and mask structure are stored						
Example script:	<pre> chdir('C:\addip\radiograms'); % reading the image original = imread('TestSample_2_3.tif'); % displaying it on the screen (without scaling) handle1 = imshow('original',original,0); % defects detection by means of neural filter nn_out = ANNthreshold(original,'c:\addip\scripts\crossMask_33x33_ANN_ff_14_7_1.ann'); % removing small dots out_med = median(nn_out,1,5,5); % displaying result handle2 = imshow('nn',out_med,1); </pre>						
Remarks:	none						

ATH							
Syntax:							
Parameters:							
Description:	Local thresholding; operates on gray scale images; the calculation of threshold is based on discrimination analysis that separate statistically image on two classes, object and background.; output is a binary image						
References:							
List of used functions:	none						
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2007.03.20	Date of last update:	2007.03.20	Version:	1.0
History of updates:	none						
Script syntax:	<i>output = ath(input, MaskSize, ThCoef);</i>						
Script parameters:	<i>Input</i> - input image; <i>output</i> - output image <i>MaskSize</i> - size of the moving mask which contains neighborhood of selected image point <i>ThCoef</i> - threshold coefficient, that moves threshold value						
Example script:	chdir('C:\addip\radiograms'); % using adaptive thresholding a = imread('TestSample_2_3.tif'); handle = imshow('original',a,0); out_med = median(a,0,51,51); out_sub = imsub(a,out_med); out_ith = ath(out_sub,75,1550); out_med1 = median(out_ith,0,9,9); handle1 = imshow('ith',out_med1,1);						
Remarks:	none						

BDILATE							
Syntax:							
Parameters:							
Description:	Faster version of Dilate function, used with binary images.						
References:	Gonzalez R. C.: „ <i>Digital Image Processing</i> ”, Addison-Wesley Pub (Sd); 3r.e. edition (March 1992), pp. xxx-xxx						
List of used functions:							
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2007.03.20	Date of last update:	2007.03.20	Version:	1.0
History of updates:							
Script syntax:	<code>output = bdilate(input, sizex, sizey);</code>						
Script parameters:	<code>input</code> - input image <code>output</code> - output image <code>sizex</code> - x size of structural element <code>sizey</code> - y size of structural element						
Example script:	<pre> chdir('C:\addip\radiograms'); % using eikiv thresholding a = imread('TestSample_2_3.tif'); handle = imshow('original',a,0); out_med = median(a,0,51,51); out_sub = imsub(a,out_med); out_ith = eth(out_sub,35,3,10,0.97,128); out_med1 = median(out_ith,0,9,9); out_bdl = bdilate(out_med1,3,3); handle1 = imshow('ith',out_bdl,1); </pre>						
Remarks:	Structural element dimensions should have odd values. Minimum value is 3.						

BERODE							
Syntax:							
Parameters:							
Description:	Faster version of Erode function, used with binary images.						
References:							
List of used functions:							
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2007.03.20	Date of last update:	2007.03.20	Version:	1.0
History of updates:							
Script syntax:	<i>output = berode(input, sizex, sizey);</i>						
Script parameters:	<i>input</i> - input image <i>output</i> - output image <i>sizex</i> - x size of structural element <i>sizey</i> - y size of structural element						
Example script:	<pre> chdir('C:\addip\radiograms'); % using eikiv thresholding a = imread('TestSample_2_3.tif'); handle = imshow('Original',a,0); out_med = median(a,0,51,51); out_sub = imsub(a,out_med); out_ith = eth(out_sub,35,3,10,0.97,128); out_med1 = median(out_ith,0,9,9); out_ber = berode(out_med1,3,3); handle1 = imshow('Binary Erode',out_ber,1); </pre>						
Remarks:	Structural element dimensions should have odd values. Minimum value is 3.						

CALCFEAT							
Syntax:							
Parameters:							
Description:	Calculating features; output number of classified defects; table with defects features; (new version of the CALCFEATURES)						
References:							
List of used functions:	none						
File name (C-code):				DLL – library name:	calcfestat.dll		
Developed by:	PSz	Date of development:	2007.03.20	Date of last update:	2007.09.26	Version:	1.0
History of updates:	None						
Script syntax:	[number, tab] = calcfestat(inpImage, indImage, binImage, min, max);						
Script parameters:	<i>inpImage</i> - input original image <i>indImage</i> - image after function index <i>binImage</i> – binary image <i>tab</i> – output table with features <i>min, max</i> – min and max size of defects <i>number</i> – number of defects						
Example script:	<pre> chdir('C:\W'); % read the image original = imread('TestSample_2_3.tif'); % and display it on the screen (without scaling) handle1 = imshow('original',original,0); % median filtering med = fastmedian(original,51,51); % subtracting filtered image from original image sub = imsub(original,med); % iterative thresholding th = ith(sub,0.8); % removing small dots out_med = fastmedian(th,5,5); % recognizing flaws indexed_image = index(out_med); [num,tab] = calcfestat(original,indexed_image,out_med,30,100000); savefeat(tab,num,'wynik.txt'); im_f = genindexedimg(original,tab,num); % displaying result handle2 = imshow('ith',out_med,1); handle3 = imshow('numbered',im_f,0); </pre>						
Remarks:							

CF							
Syntax:							
Parameters:							
Description:	New version of calfeat. This function supports multithreading and has fixed many errors.						
References:							
List of used functions:	none						
File name (C-code):				DLL – library name:	cf.dll		
Developed by:	PSz	Date of development:	2009.03.20	Date of last update:	2009.09.26	Version:	1.0
History of updates:	None						
Script syntax:	[<i>number</i> , <i>tab</i>] = calfeat (<i>org_image</i> , <i>indexed_image</i> , <i>binary_image</i>);						
Script parameters:	<i>org_image</i> - input original image <i>indexed_image</i> - image after indexing <i>binary_image</i> – binary image - after thresholding <i>tab</i> – output table with features						
Example script:	<pre> threads(4); chdir('C:\'); org=readtiff('wzorzec.tif'); bw = readtiff('wzorzec.tif'); ind = index(bw); handle3 = imshow('org',org,1); handle4 = imshow('ind',ind,1); writetiff(ind,'ind.tif',0); c = cf(org,ind,bw); matrixwrite(c,'features_out.m'); </pre>						
Remarks:							

CHDIR							
Syntax:							
Parameters:							
Description:	The chdir function changes the current working directory to the directory specified by <i>dirname</i> . The <i>dirname</i> parameter must refer to an existing directory.						
References:							
List of used functions:	none						
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2007.03.20	Date of last update:	2007.03.20	Version:	1.0
History of updates:	none						
Script syntax:	chdir ('dirname');						
Script parameters:	<i>dirname</i> – new directory						
Example script:	<pre>% read the image using full path original1 = imread('h:\nn\TestSample_1_1.tif'); % set working directory chdir('h:\nn'); % then read image using only file name original2 = imread('TestSample_1_1.tif');</pre>						
Remarks:	This function affects all input/output operations in the whole program (eg, dump, imwrite)						

CROPIMAGE							
Syntax:							
Parameters:							
Description:	Crop Image to smaller size. The white area around the weld image is removed.						
References:							
List of used functions:							
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2007.12.3	Date of last update:	2008.04.01	Version:	4.0
History of updates:	none						
Script syntax:	<i>output</i> = cropImage (<i>input</i> , <i>GrayValueThreshold</i>);						
Script parameters:	<i>input</i> - input image <i>GrayValueThreshold</i> – a threshold of gray value, over whose all pixels are cropped <i>output</i> - cropped output image						
Example script:	chdir('C:\'); a = imread('FilmFree_A_Szczecin_NA_NA_NA_TC_Spoiny_27-09-2007_14-40-04_171A.tif'); handle = imshow('original',a,1); b = cropImage(a, 60000); handle1 = imshow('cropped',b,1);						
Remarks:	none						

CUTROI							
Syntax:							
Parameters:							
Description:	Extracts sub-image laying between <i>xstart</i> - <i>xstop</i> and <i>ystart</i> - <i>ystop</i> coordinates from the original image. If extracted region is saved, the <i>Startx</i> and <i>Starty</i> coordinates are stored in a tiff file in tags TIFFTAG_XPOSITION and TIFFTAG_YPOSITION						
References:							
List of used functions:	none						
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2007.03.20	Date of last update:	2007.03.20	Version:	1.0
History of updates:	none						
Script syntax:	<i>output</i> = cutroi (<i>input</i> , <i>startx</i> , <i>stopx</i> , <i>starty</i> , <i>stopy</i>);						
Script parameters:	<i>input</i> – input image <i>output</i> – cut output image <i>startx</i> – beginning x coordinate <i>stopx</i> – ending x coordinate <i>starty</i> – beginning y coordinate <i>stopy</i> – ending y coordinate						
Example script:	<pre>original = imread('c:\\TestSample_2.3.tif'); handle1 = imshow('original',original,0); cut = cutroi(original,100,200,100,200); handle1 = imshow('cut',cut,0);</pre>						
Remarks:	none						

DETECTROI							
Syntax:							
Parameters:							
Description:	Detects a ROI using gauss function fitted to specified weld profile. By data received from a gauss a middle and edge area of weld are detected. Also heating area is set.						
References:							
List of used functions:							
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2007.10.1	Date of last update:	2007.10.1	Version:	1.0
History of updates:	none						
Script syntax:	$[ReginVectors, MedRegionVector, output] =$ detectROI(<i>input</i> , <i>dy</i> , <i>Ha</i> , <i>ImRes</i> , <i>Hup</i> , <i>Hdown</i> , <i>ErrorLim</i> , 'filename');						
Script parameters:	<i>input</i> - input image <i>output</i> - output image with weld area lines <i>dy</i> - leap between to analyzed weld profiles, it specified y size (y size = y image resolution / dy) of the RegionVectors ; <i>Ha</i> - heat area (mm) <i>ImRes</i> - image resolution (μm) <i>Hup</i> - parameter that specifies a position of central weld area (%) <i>Hdown</i> - parameter that specifies a position of weld edges <i>ErrorLim</i> - limit of error (nor use int this version, set as 0) 'filename' - name of the file and directory that contains approximation parameters <i>ReginVectors</i> – matrix containing a information of weld area lines position for each analyzed line profile [7,y size] <i>MedRegionVector</i> - matrix containing a median value of <i>ReginVectors</i> for each row						
Example script:	chdir('c:\\Test Welds - Technic Control\\'); im = imread('FIB94B.TIF'); imcut = cutroi(im,101,2999,101,1899); handle1 = imshow('imcut',imcut,1); [tab1,tab2,Roi] = detectROI(imcut,90,10,50,10,20,0,'C:\\ProgramFiles\\PSz\\ADDIP\\ADDIP\\DLL\\ApproximationParam.txt'); handle2 = imshow('Roi',Roi,0); imwrite('c:\\Test Welds - Technic Control\\FIB94B_ROI.tif',Roi);						
Remarks:	none						

DILATE							
Syntax:							
Parameters:							
Description:	Dilates input image using rectangular structural element with size specified by user. Operates on grayscale images.						
References:							
List of used functions:							
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2007.03.20	Date of last update:	2007.03.20	Version:	1.0
History of updates:							
Script syntax:	<i>output = dilate(input, sizex, sizey);</i>						
Script parameters:	<i>input</i> - input image <i>output</i> - output image <i>sizex</i> - x size of structural element <i>sizey</i> - y size of structural element						
Example script:	chdir('C:\addip\radiograms'); a = imread('TestSample_2_3.tif'); handle = imshow('Original',a,0); out_dil = dilate(a,3,3); handle1 = imshow('Dilate',out_dil,1);						
Remarks:	Structural element dimensions should have odd values. Minimum value is 3.						

DM							
Syntax:							
Parameters:							
Description:	Allows user to input matrixes directly to ADDIP workspace.						
References:							
List of used functions:	none						
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2007.08.03	Date of last update:	2007.08.03	Version:	0.9
History of updates:	none						
Script syntax:	<i>matrix = dm('matrix_def');</i>						
Script parameters:	<i>matrix – output matrix matrix_def – string that defines the matrix</i>						
Example script:	<i>Matrix = dm('1,1,1;2,1,3');</i> <i>% now matrix is 1 1 1</i> <i>% 2 1 2</i>						
Remarks:	Use [] to concentrate numbers into matrix. Commas define columns whereas ; defines next row.						

ERODE							
Syntax:							
Parameters:							
Description:	Erodes input image using rectangular structural element with size specified by user. Operates on grayscale images.						
References:							
List of used functions:							
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2007.03.20	Date of last update:	2007.03.20	Version:	1.0
History of updates:							
Script syntax:	<i>output = erode(input, sizex, sizey);</i>						
Script parameters:	<i>input</i> - input image <i>output</i> - output image <i>sizex</i> - x size of structural element <i>sizey</i> - y size of structural element						
Example script:	chdir('C:\addip\radiograms'); a = imread('TestSample_2_3.tif'); handle = imshow('Original',a,0); out_erd = erode (a,3,3); handle1 = imshow('Erode',out_erd,1);						
Remarks:	Structural element dimensions should have odd values. Minimum value is 3.						

ETH							
Syntax:							
Parameters:							
Description:	Local thresholding; thresholding; operates on gray scale images; the threshold is calculated for each area assigned to a small mask, using Otsu Threshold algorithm on data taken from area assigned to large mask; output is a binary image						
References:							
List of used functions:	none						
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2007.03.20	Date of last update:	2007.03.20	Version:	1.0
History of updates:	none						
Script syntax:	<i>output = eth(input, LargeMaskSize, SmallMaskSize, minDiff, ThCoef, GrayScaleLevels);</i>						
Script parameters:	<i>Input</i> - input image; <i>output</i> - output image <i>SmallMaskSize</i> – size of small moving mask, that is being thresholded <i>LargeMaskSize</i> – size of the large moving mask, that contain data to calculate threshold <i>minDiff</i> – minimum difference between mean value of background and mean value of object information <i>ThCoef</i> – threshold coefficient, that moves threshold value <i>GrayScaleLevels</i> – number of gray levels, that image is normalized to						
Example script:	chdir('C:\addip\radiograms'); % using eikiv thresholding a = imread('TestSample_2_3.tif'); handle = imshow('original',a,0); out_med = median(a,0,51,51); out_sub = imsub(a,out_med); out_ith = eth(out_sub,35,3,10,0.97,128); out_med1 = median(out_ith,0,9,9); handle1 = imshow('ith',out_med1,1);						
Remarks:	none						

EXIT							
Syntax:							
Parameters:							
Description:	Closes main program and passes error code to the system						
References:							
List of used functions:	none						
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2007.03.20	Date of last update:	2007.03.20	Version:	1.0
History of updates:	none						
Script syntax:	exit (<i>code</i>);						
Script parameters:	<i>code</i> - system error code (0 – no error);						
Example script:	exit (0)						
Remarks:	none						

FASTMEDIAN							
Syntax:							
Parameters:							
Description:	2-D Median filter; quick-sort algorithm; operates on gray scale images; output image has the same size as input; In next position of mask one column is sorted, previous data are stored						
References:							
List of used functions:	none						
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2007.03.20	Date of last update:	2007.03.20	Version:	1.3
History of updates:	none						
Script syntax:	<i>output</i> = fastmedian _ <i>(input, type, XmaskSize, YmaskSize)</i> ;						
Script parameters:	<i>input</i> - input image <i>output</i> - output image <i>type</i> - not used yet <i>XmaskSize</i> - x size of a mask <i>YmaskSize</i> - y size of a mask						
Example script:	chdir('C:\addip\radiograms'); a = imread('TestSample_2_3.tif'); handle = imshow('original',a,0); out_med = fastmedian (a,0,51,51); handle1 = imshow('ith',out_med,0);						
Remarks:	none						

FASTMEDIANMP							
Syntax:							
Parameters:							
Description:	2-D Median filter; quick-sort algorithm; operates on gray scale images; output image has the same size as input; In next position of mask one column is sorted, previous data are stored. This version supports multithreading (up to 2 cores). Especially suitable for images having number of columns >> number of rows						
References:							
List of used functions:	none						
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2007.03.20	Date of last update:	2007.03.20	Version:	1.3
History of updates:	none						
Script syntax:	<i>output</i> = fastmedianmp (<i>input</i> , <i>type</i> , <i>XmaskSize</i> , <i>YmaskSize</i>);						
Script parameters:	<i>input</i> - input image <i>output</i> - output image <i>type</i> - not used yet <i>XmaskSize</i> - x size of a mask <i>YmaskSize</i> - y size of a mask						
Example script:	chdir('C:\addip\radiograms'); <i>a</i> = imread('TestSample_2_3.tif'); <i>handle</i> = imshow('original', <i>a</i> ,0); <i>out_med</i> = fastmedianmp (<i>a</i> ,0,51,51); <i>handle1</i> = imshow('ith', <i>out_med</i> ,0);						
Remarks:	none						

FFTFILT							
Syntax:							
Parameters:							
Description:	Performs a low-pas, band-pass or high-pass filtering on the original image using forward and reverse transform. The cutoff frequency is normalized to 0-1 range, where 1 stands for the higher Fourier coefficient number. The transform resolution always equals the image resolution.						
References:	FFTW library documentation						
List of used functions:	none						
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2007.03.20	Date of last update:	2007.03.20	Version:	1.5
History of updates:	none						
Script syntax:	<i>[filtered, flipped] = fftfilt(image, cutoff1, cutoff2);</i>						
Script parameters:	<i>image</i> – original image <i>filtered</i> – filtered image <i>flipped</i> – extended image (for test only) <i>cutoff1</i> – lower cutoff frequency related to image size (cut-off frequency of hi-pass filter) <i>cutoff2</i> – upper cutoff frequency related to image size (cut-off frequency of lo-pass filter)						
Example script:	<pre>chdir('C:\addip\radiograms'); original = imread('c:\TestSample_2_3.tif'); ee1 = imshow('original',original,1); [outlo,zer] = fftfilt(original,0.1,5); [outhi,zer] = fftfilt(original,3,500); h = imshow('lo',outlo,1); h1 = imshow('extended',zer,1); h2 = imshow('hir',outhi,1); imwrite('c:\out.tif',outlo,1);</pre>						
Remarks:	none						

FILLHOLES							
Syntax:							
Parameters:							
Description:	Fills every closed holes in objects. Operates on binary images.						
References:							
List of used functions:							
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2007.03.20	Date of last update:	2007.03.20	Version:	1.0
History of updates:							
Script syntax:	<i>output</i> = fillholes (<i>input</i>);						
Script parameters:	<i>input</i> - input image <i>output</i> - output image						
Example script:							
Remarks:							

GENINDEXEDIMG							
Syntax:							
Parameters:							
Description:	Generates image with shown defects; (new version of GENINDEXIMAGE)						
References:							
List of used functions:	none						
File name (C-code):				DLL – library name:	genindexedingm.dll		
Developed by:	PSz	Date of development:	2007.03.20	Date of last update:	2007.09.26	Version:	1.0
History of updates:	None						
Script syntax:	genindexeding (<i>inplImage, binImage, tab, number, color</i>)						
Script parameters:	<i>inplImage</i> - input original image <i>binImage</i> – binary image <i>tab</i> – table with features <i>number</i> – number of defects <i>color</i> – color of the description text and outline						
Example script:	<pre> chdir('C:\W'); % read the image original = imread('TestSample_2_3.tif'); % and display it on the screen (without scaling) handle1 = imshow('original',original,0); % median filtering med = fastmedian(original,51,51); % subtracting filtered image from original image sub = imsub(original,med); % iterative thresholding th = ith(sub,0.8); % removing small dots out_med = fastmedian(th,5,5); % recognizing flaws indexed_image = index(out_med); [num,tab] = calcfeat(original,indexed_image,out_med,30,100000); savefeat(tab,num,'wynik.txt'); im_f= genindexeding(original,tab,num); % displaying result handle2 = imshow('ith',out_med,1); handle3 = imshow('numbered',im_f,0); </pre>						
Remarks:	none						

GETIMSIZE							
Syntax:							
Parameters:							
Description:	Returns size of the image						
References:							
List of used functions:	none						
File name (C-code):			DLL – library name:	Getimsizedll			
Developed by:	PSz	Date of development:	2007.10.28	Date of last update:	2007.10.28	Version:	1.0
History of updates:	none						
Script syntax:	<code>[rows,cols] = getimsized(image);</code>						
Script parameters:	<i>image</i> – input image <i>rows</i> – number of rows in <i>image</i> <i>cols</i> – number of columns in <i>image</i>						
Example script:	<pre>chdir('C:\\addip\\radiograms'); a = readtiff('TestSample_2_3.tif'); [rows,cols] = getimsized(image); matrixwrite(row,'row.txt'); matrixwrite(col,'col.txt');</pre>						
Remarks:	none						

GETMATRIXELEMENT							
Syntax:							
Parameters:							
Description:	Extracts one or more elements from matrix. Elements in matrix are indexed from 0. Function accepts particular number of row and column as well as matrices that contain indexes of elements to cut.						
References:							
List of used functions:	none						
File name (C-code):				DLL – library name:	Getmatrixelement.dll		
Developed by:	PSz	Date of development:	2007.10.28	Date of last update:	2007.10.28	Version:	1.0
History of updates:	none						
Script syntax:	<i>out</i> = getmatrixelement (<i>matrix</i> , <i>rows</i> , <i>cols</i>);						
Script parameters:	<i>matrix</i> – input matrix <i>out</i> – extracted elements from <i>matrix</i> <i>rows</i> – vector of size1xR with indexes of <i>matrix</i> elements to cut. R must be smaller than number of rows in <i>matrix</i> <i>cols</i> – vector of size1xC with indexes of <i>matrix</i> elements to cut. C must be smaller than number of columns in <i>matrix</i>						
Example script:	<pre> a = dm('1,2,3,4,5; 6,7,8,9,10'); % extracting one element from first row and second column out1 = getmatrixelement(a,0,1); % extracting three elements from second row c = dm('1,2,3'); out2 = getmatrixelement(a,1,c); matrixwrite(out1,'out1.txt'); matrixwrite(out2,'out2.txt');</pre>						
Remarks:	none						

GTH							
Syntax:							
Parameters:							
Description:	Global thresholding; operates on gray scale images; the threshold is calculated according to the maximum gradient of brightness in x and y direction; output is a binary image						
References:							
List of used functions:	none						
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2007.03.20	Date of last update:	2007.03.20	Version:	1.0
History of updates:	none						
Script syntax:	<i>output</i> = gth (<i>input</i> , <i>MaskSize</i> , <i>ThCoef</i>);						
Script parameters:	<i>input</i> - input image; <i>output</i> - output image with a 0,1 binary information where 1 is object and 0 is a background <i>MaskSize</i> - size of the moving mask which contains neighborhood of selected image point (odd) <i>ThCoef</i> - threshold coefficient, that moves threshold value						
Example script:	<pre> chdir('C:\addip\radiograms'); % using gradient thresholding a = imread('TestSample_2_3.tif'); handle = imshow('original',a,0); out_med = median(a,0,51,51); out_sub = imsub(a,out_med); out_ith = gth(out_sub,31,0.75); out_med1 = median(out_ith,0,9,9); handle1 = imshow('ith',out_med1,1); </pre>						
Remarks:	none						

HIST							
Syntax:							
Parameters:							
Description:	Displays histogram of the image in the separate window. All values are multiplied by <i>mag</i> before displaying. The output window has a fixed size and can't be resized.						
References:							
List of used functions:	none						
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2007.03.20	Date of last update:	2007.03.20	Version:	1.0
History of updates:	none						
Script syntax:	hist (<i>image</i> , <i>mag</i>);						
Script parameters:	<i>image</i> - original image <i>mag</i> - magnification						
Example script:	chdir('C:\\addip\\radiograms'); % read the image original = imread('TestSample_1_1.tif'); % histogram in original scale hist (original,1); % half-sized histogram hist (image,0.5);						
Remarks:	none						

IMADD							
Syntax:							
Parameters:							
Description:	Adds two images. The input images are normalized to 0-65535 range before adding. Result is normalized as well. The <i>image1</i> and <i>image2</i> must be the same size.						
References:							
List of used functions:	none						
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2007.03.20	Date of last update:	2007.03.20	Version:	1.0
History of updates:	none						
Script syntax:	<i>output = imadd(image1, image1);</i>						
Script parameters:	<i>image1</i> – original image <i>image2</i> – original image <i>output</i> – sum of <i>image1</i> and <i>image2</i>						
Example script:	<pre> chdir('C:\addip\radiograms'); % read the image original1 = imread('TestSample_1_1.tif'); % read the image original2 = imread('TestSample_1_2.tif'); % adding images output = imadd(original1, original2); % displaying the result handle1 = imshow('adding result', output,1); </pre>						
Remarks:	none						

IMCLOSE							
Syntax:							
Parameters:							
Description:	Closes the window identified by <i>handle</i> .						
References:	OpenCV Library documentation						
List of used functions:	none						
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2007.03.20	Date of last update:	2007.03.20	Version:	1.0
History of updates:	none						
Script syntax:	imclose (<i>handle</i>);						
Script parameters:	<i>handle</i> – a handle returned by imread function						
Example script:	<pre> chdir('C:\\addip\\radiograms'); % read the image original1 = imread('TestSample_1_1.tif'); % closing imclose(original1); % to see the window opened by imread one must run the program step-by-step </pre>						
Remarks:	Useful only during step-by-step running						

IMMULTI							
Syntax:							
Parameters:							
Description:	Multiplies image1 by image1. The input images are normalized to 0-65535 range before multiplying. Result is normalized as well. The image1 and image2 must have the same size.						
References:							
List of used functions:	none						
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2007.03.20	Date of last update:	2007.03.20	Version:	1.0
History of updates:	none						
Script syntax:	<i>output = immulti(image1, image1);</i>						
Script parameters:	<i>image1</i> – original image <i>image2</i> – original image <i>output</i> – sum of image1 and image2						
Example script:	<pre> chdir('C:\addip\radiograms'); % read the image original1 = imread('TestSample_1_1.tif'); % read the image original2 = imread('TestSample_1_2.tif'); % multiplying images output = immulti(original1, original2); % displaying the result handle1 = imshow('multiplication result', output,1); </pre>						
Remarks:	none						

IMNORMALIZE							
Syntax:							
Parameters:							
Description:	Image normalization procedure. It is base on rigidly determine the background gray value and stretching the histogram from that point.						
References:							
List of used functions:	none						
File name (C-code):				DLL – library name:	imNormalize.dll		
Developed by:	PSz	Date of development:	2009.03.13	Date of last update:	2009.03.13	Version:	1.0
History of updates:	None						
Script syntax:	<pre>reg=dm('x1,y1,x2,y2'); outimage = imNormalize(inpImage, GrayLvl,reg , deltaIBase, Nmin, randLayout,IBaseShift);</pre>						
Script parameters:	<p><i>inpImage</i> - input original image, <i>GrayLvl</i> – maximum gray level value of input image, <i>reg</i> - region of interest, that calculates IBase (backgroung value), if reg = [0,0,0,0] the background IBase is calculated according to histogram and deltaIBase, <i>deltaIBase</i> – range of determine the IBase value on a histogram , <i>Nmin</i> - relative minimum on histogram taken to a consideration , <i>randLayout</i> – random percentage edge value of a histogram. All pixels with < Nmin are set on the edge. If randLayout = 0 these pixels are set on a value = Mmin or Nmax, <i>IBaseShift</i> – target IBase shifted from IBase, during the stretch operations the IBaseShift reminds in the same place</p>						
Example script:	<pre>chdir(C:\Program Files\PSz\ADDIP_FilmFree\ADDIP\Radiograms'); inIm = readtiff('T_14-32-53_836A.tif'); reg = dm('[0,0,0,0]'); outIm=imNormalize(inIm,65535,reg,9,2,0,20000); handle0 = imshow('inIm',inIm,0); handle1 = imshow('outIm',outIm,0);</pre>						
Remarks:							

IMPORTBINARYMATRIX							
Syntax:							
Parameters:							
Description:	Imports matrix from Matlab to ADDIP. Save matrix in Matlab using savebinarymatrix.m script						
References:							
List of used functions:	none						
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2007.03.20	Date of last update:	2007.03.20	Version:	1.0
History of updates:	none						
Script syntax:	<i>output</i> = importbinarymatrix ('matrix.txt');						
Script parameters:	<i>matrix.txt</i> – filename						
Example script:	%						
Remarks:	none						

IMREAD							
Syntax:							
Parameters:							
Description:	Imread reads grayscale or BW image in 16-bit tiff format						
References:	Libtiff documentation and internet resources.						
List of used functions:	none						
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2007.03.20	Date of last update:	2007.03.20	Version:	1.0
History of updates:	none						
Script syntax:	<i>Image</i> = imread (<i>filename</i>);						
Script parameters:	<i>filename</i> – path and name of the tiff file; <i>image</i> – opened image						
Example script:	<pre> chdir('C:\addip\radiograms'); % read the image original = imread('TestSample_2_3.tif'); % and display it on the screen (without scaling) handle1 = imshow('original',original,0); % median filtering med = median(original,0,51,51); % save result to file imwrite('c:\test.tif', med,1); </pre>						
Remarks:	none						

IMSHOW							
Syntax:							
Parameters:							
Description:	Displays image on the screen. The images bigger than 1280x1024 are automatically scaled to this size.						
References:	OpenCV Library documentation						
List of used functions:	none						
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2007.03.20	Date of last update:	2007.03.20	Version:	1.0
History of updates:	none						
Script syntax:	<i>handle = imshow('name', image, norm);</i>						
Script parameters:	<i>name</i> – window name displayed in the title bar <i>image</i> – the image to be displayed <i>handle</i> – handle to identify the window <i>norm</i> – data range normalization 0 – without normalization – display image as it is 1 – with normalization – image values are scaled to range 0 - 65535						
Example script:	<pre> chdir('C:\addip\radiograms'); % read the image original1 = imread('TestSample_1_1.tif'); % read the binary image original2 = imread('TestSample_1_bin.tif'); % display grayscale image H1 = imshow('original1', original1, 0); % displaying the binary image H2 = imshow('original2', original2, 1); </pre>						
Remarks:	The maximal size opened window is 1280x1024. Bigger images are scaled to this resolution. Screen resolution should be 1280x1024 or bigger. Two windows can't have the same names. If they have, second window erases first window.						

IMSUB							
Syntax:							
Parameters:							
Description:	Subtracts <i>image2</i> from <i>image1</i> . The input images are normalized to 0-65535 range before subtracting. Result is normalized as well. The <i>image1</i> and <i>image2</i> must have the same size						
References:							
List of used functions:	none						
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2007.03.20	Date of last update:	2007.03.20	Version:	1.0
History of updates:	none						
Script syntax:	<i>output</i> = imsub (<i>image1</i> , <i>image1</i>);						
Script parameters:	<i>image1</i> – original image <i>image2</i> – original image <i>output</i> – sum of <i>image1</i> and <i>image2</i>						
Example script:	chdir('C:\addip\radiograms'); % read the image original1 = imread('TestSample_1_1.tif'); % read the image original2 = imread('TestSample_1_2.tif'); % adding images output = imsub (original1, original2); % displaying the result handle1 = imshow('subtracting result', output,1);						
Remarks:	none						

IMWRITE							
Syntax:							
Parameters:							
Description:	Imwrite saves grayscale or BW image on the disk in 16-bit tiff format						
References:	Libtiff documentation and internet resources.						
List of used functions:	none						
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2007.03.20	Date of last update:	2007.03.20	Version:	1.0
History of updates:	none						
Script syntax:	imwrite (filename, image, normalization);						
Script parameters:	filename – path and name of the tiff file; output – image to save normalization – 0 – without normalization, 1 –linear normalization to range 0-65535						
Example script:	<pre> chdir('C:\\addip\\radiograms'); % read the image original = imread('TestSample_2_3.tif'); % and display it on the screen (without scaling) handle1 = imshow('original',original,0); % median filtering med = median(original,0,51,51); % save result to file imwrite('c:\\test.tif', med,1); </pre>						
Remarks:	none						

INDEX							
Syntax:							
Parameters:							
Description:	segmentation; operates on binary; output image has the same size as input.						
References:	R. Tadasiewicz and P. Korohoda "Komputerowa analiza i przetwarzanie obrazów"						
List of used functions:							
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2007.03.20	Date of last update:	2007.03.20	Version:	1.0
History of updates:	None						
Script syntax:	<i>output</i> = index (<i>input</i>);						
Script parameters:	<i>input</i> - input binary image <i>output</i> - output image						
Example script:	<pre> chdir('C:\\addip\\radiograms'); % read the image original = imread('TestSample_2_3.tif'); % and display it on the screen (without scaling) handle1 = imshow('original',original,0); % median filtering med = fastmedian(original,51,51); % subtracting filtered image from original image sub = imsub(original,med); % iterative thresholding th = ith(sub,0.8); % removing small dots out_med = fastmedian(th,5,5); % recognizing flaws indexed_image = index(out_med); [tab,num] = calcfeatures(original,indexed_image,out_med,1,100000); savefeatures(tab,num,'wynik.txt'); im_f= genindexedimage(original,tab,num); % displaying result handle2 = imshow('ith',out_med,1); handle3 = imshow('numbered',im_f,0); </pre>						
Remarks:	none						

INVERSE							
Syntax:							
Parameters:							
Description:	Inverts color map of input image.						
References:							
List of used functions:	none						
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2008.03.03	Date of last update:	2008.03.03	Version:	1.0
History of updates:	none						
Script syntax:	<i>output</i> = inverse (<i>image1</i>);						
Script parameters:	<i>image1</i> – original image <i>output</i> – inverted image						
Example script:	<pre> chdir('C:\addip\radiograms'); original = readtiff('TestIm2.1.tif'); ee1 = imshow('original',original,1); inv inverse(original); h2 = imshow('inv',inv,1); </pre>						
Remarks:	none						

ISeeCommand							
Syntax:							
Parameters:							
Description:	Sending commands to ISee! via telnet interface. Full list of commands available at: http://www.kb.bam.de/~alex/interfacing-with-ic/						
References:							
List of used functions:	none						
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2009.03.12	Date of last update:	2009.03.12	Version:	1.0
History of updates:	none						
Script syntax:	<i>output</i> = ISeeCommand (<i>command</i>);						
Script parameters:	<i>command</i> - valid ISee!'s telnet command; <i>output</i> - ISee!'s answer						
Example script:	<pre>% setting port for communication iseeport(23); % Creating dataset file a = ISeeCommand('savedatasetas c:/set.txt'); % Extracting image file's name from dataset file nazwa = ISeeGetFile('c:/set.txt'); A = readtiff(nazwa); % Extracting first ROI from image basing on dataset file A = ISeeGetROI(A, 'c:/set.txt', 1); handle = imshow('okno', A, 1); writetiff(A, 'C:\a.tif', 0); % Opening modified image in ISee! b = ISeeCommand('loadimage c:/a.tif');</pre>						
Remarks:	None						

ISeeGetFile							
Syntax:							
Parameters:							
Description:	Extraction of image file's name from ISee!'s dataset file, along with it's conversion to ADDIP format.						
References:							
List of used functions:	none						
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2009.03.12	Date of last update:	2009.03.12	Version:	1.0
History of updates:	none						
Script syntax:	<i>output</i> = ISeeGetFile (fileName);						
Script parameters:	<i>fileName</i> - name of ISee!'s dataset file; <i>output</i> - name of image file retrieved from dataset file and converted to ADDIP format						
Example script:	<pre> % setting port for communication iseeport(23); % Creating dataset file a = ISeeCommand('savedatasetas c:/set.txt'); % Extracting image file's name from dataset file nazwa = ISeeGetFile('c:/set.txt'); A = readtiff(nazwa); % Extracting first ROI from image basing on dataset file A = ISeeGetROI(A, 'c:/set.txt', 1); handle = imshow('okno', A, 1); writetiff(A, 'C:\\a.tif', 0); % Opening modified image in ISee! b = ISeeCommand('loadimage c:/a.tif'); </pre>						
Remarks:	none						

ISeeGetROI							
Syntax:							
Parameters:							
Description:	Extraction of desired ISee!'s ROI, given: image, ISee!'s dataset file and ROI's number.						
References:							
List of used functions:	none						
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2009.03.12	Date of last update:	2009.03.12	Version:	1.0
History of updates:	none						
Script syntax:	<i>output = ISeeGetROI(image, fileName, roi);</i>						
Script parameters:	<i>image</i> - image, from which desired ROI is extracted; <i>fileName</i> - name of ISee!'s dataset file (containing information about ROI's) <i>roi</i> - ROI's number in ISee! <i>output</i> - desired part of input image. If ROI with specified number does not exist in dataset file, whole input image is returned instead.						
Example script:	<pre>% setting port for communication iseeport(23); % Creating dataset file a = ISeeCommand('savedatasetas c:/set.txt'); % Extracting image file's name from dataset file nazwa = ISeeGetFile('c:/set.txt'); A = readtiff(nazwa); % Extracting first ROI from image basing on dataset file A = ISeeGetROI(A, 'c:/set.txt', 1); handle = imshow('okno', A, 1); writetiff(A, 'C:\a.tif', 0); % Opening modified image in ISee! b = ISeeCommand('loadimage c:/a.tif');</pre>						
Remarks:	none						

ISEEPORT							
Syntax:							
Parameters:							
Description:	This function initializes global variable <i>iseeport</i> . Global variables are available for all other functions.						
References:							
List of used functions:	none						
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2009.01.15	Date of last update:		Version:	1.0
History of updates:	none						
Script syntax:	<i>iseeport(port);</i>						
Script parameters:	<i>port</i> – port number						
Example script:							
Remarks:	none						

ITH							
Syntax:							
Parameters:							
Description:	Global thresholding; operates on gray scale images; the threshold is calculated using bimodal distribution of image histogram.; output is a binary image						
References:							
List of used functions:	none						
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2007.03.20	Date of last update:	2007.03.20	Version:	1.0
History of updates:	none						
Script syntax:	<i>output</i> = ith (<i>input</i> , <i>ThCoef</i>);						
Script parameters:	<i>input</i> - input image; <i>output</i> - output image with a 0,1 binary information where 1 is object and 0 is a background <i>ThCoef</i> - threshold coefficient, that moves threshold value						
Example script:	chdir('C:\addip\radiograms'); % using iterative thresholding a = imread('TestSample_2_3.tif'); handle = imshow('original',a,0); out_med = median(a,0,51,51); out_sub = imsub(a,out_med); out_ith = ith (out_sub,0.8); out_med1 = median(out_ith,0,9,9); handle1 = imshow('ith',out_med1,1);						
Remarks:	none						

IQIDET							
Syntax:							
Parameters:							
Description:	Improves detection of IQIs						
References:							
List of used functions:							
File name (C-code):				DLL – library name:	iqidet.dll		
Developed by:	PSz	Date of development:	2007.10.01	Date of last update:	2007.10.01	Version:	1.0
History of updates:							
Script syntax:	<i>output = iqidet(input,angle,width,num);</i>						
Script parameters:	<i>input</i> - input image <i>output</i> - output image <i>angle</i> - maximum predicted angle of IQI <i>width</i> - width of moving mask <i>num</i> - width of detecting strip						
Example script:	chdir('C:\addip\radiograms'); % read image a = readtiff('IQI_02.tif'); handle = imshow('original',a,1); % IQI detection iqi = iqidet(a,10,7,3); handle1 = imshow('iqi',iqi,0);						
Remarks:	Width and num parameter must be an odd values. Effective angle can be set from range <-15;15> degrees. Num parameter must be smaller than width. Function parameters deployed in iq_i_out.txt file in working directory.						

IQIMAX							
Syntax:							
Parameters:							
Description:	IQImax function find a maximum value of IQIs. It calculates a median value of every visible wire and its position. This function also calculates SNR for each wire.						
References:							
List of used functions:							
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2007.10.7	Date of last update:	2007.10.7	Version:	2.0
History of updates:	none						
Script syntax:	<i>output</i> = IQImax (<i>input_bef</i> , <i>input_aft</i> , <i>Resolution</i> , <i>WireNr</i> , <i>VisibleWires</i> , ' <i>filename</i> ');						
Script parameters:	<i>input_bef</i> - input image before using median filter <i>input_aft</i> - input image after using median filter <i>output</i> - output image ,a black image with white middles of visible wires <i>Resolution</i> - image resolution (μm) <i>WireNr</i> - model of number of following wires (W1, W6, W10, W13) <i>VisibleWire</i> – number of visible wires (1-7) ' <i>filename</i> ' - name of the file and directory where results will be save						
Example script:	chdir('C:\Test Welds - Technic Control\IQI'); original1 = imread('iqi_test_aft.tif'); handle1 = imshow('original1',original1,0); iqiImage =IQImax(original1,50,6,6,'C:\Test Welds - Technic Control\IQIsData.txt'); handle2 = imshow('iqiImage',iqiImage,0);						
Remarks:	none						

LENGTHAREA							
Syntax:							
Parameters:							
Description:	Detects a ROI in X direction and cut image according to EN 1435 or according to specified length.						
References:							
List of used functions:							
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2007.12.3	Date of last update:	2007.12.3	Version:	2.0
History of updates:	none						
Script syntax:	<i>output</i> = lengthArea (<i>input</i> , <i>SpecL</i> , <i>WeldClass</i> , <i>WeldThickness</i> , <i>SrcDist</i> , <i>Resolution</i>);						
Script parameters:	<i>input</i> - input image <i>output</i> - output image <i>SpecL</i> - specified a length [mm] by which the weld image is shorten. If value is set to 0 this length is calculated according to EN 1435 using <i>WeldClass</i> , <i>WeldThickness</i> , <i>SrcDist</i> and <i>Resolution</i> parameters <i>WeldClass</i> - 0 class A, 1 class B <i>WeldThickness</i> - the thickness of a weld <i>SrcDist</i> - distance between X-ray source and examined component <i>Resolution</i> - image resolution (µm)						
Example script:	chdir('C:\V'); % read image a = imread('FilmFree_A_Szczecin_NA_NA_NA_TC_Spoiny_27-09-2007_14-40-04_171A.tif'); % show image handle = imshow('original',a,1); % crop with the area b = cropImage(a); % show after crop handle1 = imshow('cropped',b,1); % detect ROI according to X dimension (length of weld image) c = lengthArea(b,0,0,16,730,50); % or c = lengthArea(b,10,0,0,0,0); % show result handle2 = imshow('RoiX',c,1);						
Remarks:	none						

MATRIXREAD							
Syntax:							
Parameters:							
Description:	Reads a matrix from textfile. This command uses Matlab method of defining matrices.						
References:							
List of used functions:	none						
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2007.03.20	Date of last update:	2007.03.20	Version:	0.9
History of updates:	none						
Script syntax:	<i>matrix</i> = matrixread ('filename');						
Script parameters:	<i>matrix</i> – output matrix <i>filename</i> – name of the file with matrix						
Example script:	<p><i>Example of file matrix.txt:</i></p> <pre>[1,2;3,4]</pre> <p><i>Matrix = matrixread('matrix.txt');</i> <i>% now matrix is</i> 1 2 <i>%</i> 3 4</p>						
Remarks:	Use [] to concentrate numbers into matrix. Commas define columns whereas ; defines next row. This is obsolete function, use <i>dm</i> instead.						

MATRIXWRITE							
Syntax:							
Parameters:							
Description:	Writes a matrix to textfile. This command uses Matlab method of defining matrices.						
References:							
List of used functions:	none						
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2007.03.20	Date of last update:	2007.03.20	Version:	1.0
History of updates:	none						
Script syntax:	matrixwrite (<i>matrix</i> , ' <i>filename</i> ');						
Script parameters:	<i>matrix</i> – matrix to be written to disk <i>filename</i> – name of the file						
Example script:							
Remarks:	Use [] to concentrate numbers into matrix. Commas define columns and ; defines next row.						

MEDIAN							
Syntax:							
Parameters:							
Description:	2-D median filtering. The median command applies an two-dimensional median filter of size x x y to input image. Output image <i>output</i> has the same size as input.						
References:							
List of used functions:	none						
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2007.03.20	Date of last update:	2007.03.20	Version:	1.0
History of updates:	None						
Script syntax:	<i>output</i> = median (<i>input</i> , <i>type</i> , <i>versize</i> , <i>horsize</i>);						
Script parameters:	<i>input</i> - input binary image <i>type</i> - type of mask, 0 – rectangle, 1 – cross, 2 – X <i>versize</i> - vertical size of mask <i>horsize</i> - horizontal size of mas						
Example script:	chdir('C:\addip\radiograms'); % read the image <i>original</i> = imread('TestSample_2_3.tif'); % and display it on the screen (without scaling) <i>handle1</i> = imshow('original', <i>original</i> ,0); % median filtering <i>med</i> = median (<i>original</i> ,0,51,51); % displaying result <i>handle2</i> = imshow('ith', <i>med</i> ,0);						
Remarks:	none						

MULT_ADD							
Syntax:							
Parameters:							
Description:							
References:							
List of used functions:	none						
File name (C-code):				DLL – library name:	mult_add.dll		
Developed by:	PSz	Date of development:	2007.09.20	Date of last update:	2007.09.20	Version:	1.0
History of updates:	None						
Script syntax:	<i>outimage</i> = mult_add (<i>inplImage</i> , <i>Mult</i> , <i>Add</i>);						
Script parameters:	<i>inplImage</i> - input original image <i>Mult</i> - number which multiplies value of each pixel <i>Add</i> - number added to each value						
Example script:	<pre> chdir('C:\addip\radiograms'); or = imread('TestSample_2_3.tif'); mm = dm([0,0,0,0]); img = mult_add(or,10,33); [max,min,sred,med]=statistic(img,mm); imwrite('result.tif',img); show = imshow('result', obraz,0); savestat('stat.txt',max,min,sred,med); </pre>						
Remarks:							

NEIGHB							
Syntax:							
Parameters:							
Description:	Calculates distances between object in range specified by user.						
References:							
List of used functions:							
File name (C-code):				DLL – library name:	neighb.dll		
Developed by:	PSz	Date of development:	2008.04.18	Date of last update:	2008.04.18	Version:	1.0
History of updates:							
Script syntax:	<i>distances</i> = neighb (<i>input,range,resolution</i>);						
Script parameters:	<i>input</i> - input image (indexed) <i>distances</i> - output matrix with distances between objects <i>range</i> - user specified range <i>resolution</i> - prescale factor (millimeters<->pixels)						
Example script:	chdir('C:\addip\radiograms'); % read image <i>indexed</i> = readtiff('Ind.tif'); % distances calculation <i>list</i> = neighb (<i>indexed</i> ,50,1);						
Remarks:	When the resolution parameter is set to 1, then the output matrix contain distances in pixels, otherwise in millimeters (if this value is valid). For test purposes results matrix (results.m) and distances matrix (distances.m) are saved in main directory at drive C:\						

NEURAL							
Syntax:							
Parameters:							
Description:	Performs flaw's detection algorithm using Artificial Neural Network (ANN) technique. The filtering window moves from pixel to pixel over an input image. Acquired data (intensities of pixels) are given as an input of previously trained nonlinear neural filter. For each position of the window one point of output image is estimated. Operates on gray scale images. Output image has the same size as input.						
References:	Shaun W. Lawson, Graham A. Parker: "Intelligent segmentation of industrial radiographic images using neural networks", Proc. SPIE Vol. 2347, p. 245-255, Machine Vision Applications, Architectures, and Systems Integration III, 1994						
List of used functions:							
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2007.04.12	Date of last update:	2007.04.12	Version:	1.0
History of updates:	none						
Script syntax:	<code>output = neural(input, 'filename');</code>						
Script parameters:	<code>input</code> - input image <code>output</code> - output image <code>'filename'</code> - name of the file where the ANN and mask structure are stored						
Example script:	<pre> chdir('C:\addip\radiograms'); % reading the image original = imread('TestSample_2_3.tif'); % displaying it on the screen (without scaling) handle1 = imshow('original',original,0); % defects detection by means of neural filter nn_out = neural(original,'c:\addip\scripts\crossMask_33x33_ANN_ff_14_7_1.ann'); % removing small dots out_med = median(nn_out,1,5,5); % displaying result handle2 = imshow('nn',out_med,1); </pre>						
Remarks:	none						

NORMALIZE							
Syntax:							
Parameters:							
Description:	Normalize the input image to range of 0-1						
References:							
List of used functions:							
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2007.04.12	Date of last update:	2007.04.12	Version:	1.0
History of updates:	none						
Script syntax:	<i>output</i> = normalize (<i>input</i>);						
Script parameters:	<i>input</i> - input image <i>output</i> - output image						
Example script:	<pre> chdir('C:\addip\radiograms'); % reading the image original = imread('TestSample_2_3.tif'); % displaying it on the screen (without scaling) handle1 = imshow('original',original,0); % image normalization norm = normalize(original); % displaying result handle2 = imshow('norm',norm,0); </pre>						
Remarks:	none						

NORM_RADIO							
Syntax:							
Parameters:							
Description:	Special normalization						
References:							
List of used functions:	none						
File name (C-code):				DLL – library name:	norm_radio.dll		
Developed by:	PSz	Date of development:	2007.09.20	Date of last update:	2007.09.20	Version:	1.0
History of updates:	None						
Script syntax:	<pre>table=dm('x1,y1,x2,y2'); outimage = norm_radio(inplImage, Inum, Ibasetarget, Nmin, Dlbase, table);</pre>						
Script parameters:	<p> <i>inplImage</i> - input original image <i>Inum</i> - number of levels <i>Ibasetarget</i> - base target <i>Nmin</i> - relative minimum <i>Dlbase</i> - delta base <i>table</i> - region of interest </p>						
Example script:	<pre>chdir('C:\addip\radiograms'); or = imread('TestSample_2_3.tif'); mm = dm('0,0,0,0'); img= norm_radio(or,65535,1000,2,8,mm); [max,min,sred,med]=statistic(img,mm); imwrite('result.tif',img); drukuj = imshow('result',img,0); savestat('stat.txt',max,min,sred,med);</pre>						
Remarks:							

NTH							
Syntax:							
Parameters:							
Description:	Global thresholding; operates on gray scale images The threshold is calculated for each pixel of an image using mean value of neighbours and standard deviation, object and background.; output is a binary image						
References:							
List of used functions:	none						
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2007.03.20	Date of last update:	2007.03.20	Version:	1.0
History of updates:	none						
Script syntax:	<i>output = nth(input input, MaskSize, ThCoef);</i>						
Script parameters:	<i>Input</i> - input image; <i>output</i> - output image <i>MaskSize</i> - size of the moving mask which contains neighborhood of selected image point <i>ThCoef</i> - threshold coefficient, that moves threshold value						
Example script:	chdir('C:\addip\radiograms'); % using Niblack thresholding a = imread('TestSample_2_3.tif'); handle = imshow('original',a,0); out_med = median(a,0,51,51); out_sub = imsub(a,out_med); out_ith = nth(out_sub,41,-0.9); out_med1 = median(out_ith,0,5,5); handle1 = imshow('nth',out_med1,1);						
Remarks:	none						

OTH							
Syntax:							
Parameters:							
Description:	Global thresholding; operates on gray scale images; the calculation of threshold is based on discrimination analysis that separate statistically image on two classes, object and background.; output is a binary image						
References:							
List of used functions:	none						
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2007.03.20	Date of last update:	2007.03.20	Version:	1.0
History of updates:	none						
Script syntax:	<i>output</i> = oth (<i>input</i> , <i>ThCoef</i>);						
Script parameters:	<i>input</i> - input image; <i>output</i> - output image with a 0,1 binary information where 1 is object and 0 is a background <i>ThCoef</i> - threshold coefficient, that moves threshold value						
Example script:	chdir('C:\addip\radiograms'); % using Otsu thresholding a = imread('TestSample_2_3.tif'); handle = imshow('original',a,0); out_med = median(a,0,51,51); out_sub = imsub(a,out_med); out_ith = oth (out_sub,0.4,8); out_med1 = median(out_ith,0,9,9); handle1 = imshow('ith',out_med1,1);						
Remarks:	none						

OUTLINE							
Syntax:							
Parameters:							
Description:	Draws a border (1 pixel width) of any object on binary image.						
References:							
List of used functions:							
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2007.03.20	Date of last update:	2007.03.20	Version:	1.0
History of updates:							
Script syntax:	<i>output</i> = outline (<i>input</i>);						
Script parameters:	<i>input</i> - input image <i>output</i> - output image						
Example script:	<pre> chdir('C:\addip\radiograms'); % using eikiv thresholding a = imread('TestSample_2_3.tif'); handle = imshow('Original',a,0); out_med = median(a,0,51,51); out_sub = imsub(a,out_med); out_ith = eth(out_sub,35,3,10,0.97,128); out_med1 = median(out_ith,0,9,9); out_out = outline(out_med1); handle1 = imshow('Outline',out_out,1); </pre>						
Remarks:							

PREWITT							
Syntax:							
Parameters:							
Description:	Prewitt gradient filter.						
References:							
List of used functions:							
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2007.03.20	Date of last update:	2007.03.20	Version:	1.0
History of updates:							
Script syntax:	<i>output</i> = prewitt (<i>input</i> , <i>type</i>);						
Script parameters:	<i>Input</i> - input image; <i>output</i> - output image <i>type</i> - type of mask used (0 – horizontal or 1 - vertical)						
Example script:	chdir('C:\addip\radiograms'); <i>a</i> = imread('TestSample_2_3.tif'); <i>handle</i> = imshow('original', <i>a</i> ,0); <i>out_med</i> = median(<i>a</i> ,11,11); <i>out_prw</i> = prewitt (<i>out_med</i> ,0); <i>handle1</i> = imshow('prewitt_0', <i>out_prw</i> ,1);						
Remarks:							

READTIFF							
Syntax:							
Parameters:							
Description:	Reads 16-bit grayscale TIFF image.						
References:							
List of used functions:							
File name (C-code):				DLL – library name:	readtiff.dll		
Developed by:	PSz	Date of development:	2007.09.26	Date of last update:	2007.09.26	Version:	1.0
History of updates:	none						
Script syntax:	<i>output</i> = readtiff (' <i>filename</i> ');						
Script parameters:	<i>output</i> - image ' <i>filename</i> ' - path to the image						
Example script:	<pre> chdir('C:\addip\radiograms'); % read image original = readtiff('TestSample_3_2.tif'); % and display it on the screen (with scaling) handle1 = imshow('original',original,1); </pre>						
Remarks:	Image read by readtiff function should be displayed with scaling. Only 16-bit images can be read using this function.						

ROBERTS							
Syntax:							
Parameters:							
Description:	Roberts gradient filter.						
References:							
List of used functions:							
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2007.03.20	Date of last update:	2007.03.20	Version:	1.0
History of updates:							
Script syntax:	<i>output</i> = roberts (<i>input</i> , <i>type</i>);						
Script parameters:	<div><div><div><div><div><i>Input</i></div><div><i>output</i></div><div><i>type</i></div></div><div><div>- input image;</div><div>- output image</div><div>- type of mask used (0 –</div><div><div><div><div> </div><div>0</div><div>0</div><div>0</div><div> </div></div><div><div><div><div> </div><div>-1</div><div>0</div><div>0</div><div> </div></div><div><div><div><div> </div><div>0</div><div>1</div><div>0</div><div> </div></div><div><div><div><div> </div><div>0</div><div>0</div><div>0</div><div> </div></div><div><div><div><div> </div><div>0</div><div>0</div><div>-1</div><div> </div></div><div><div><div><div> </div><div>0</div><div>1</div><div>0</div><div> </div></div></div></div></div></div></div></div></div></div></div></div></div></div></div></div></div></div>						
Example script:	<div>chdir('C:\addip\radiograms');</div> <div><i>a</i> = imread('TestSample_2_3.tif');</div> <div><i>handle</i> = imshow('original',<i>a</i>,0);</div> <div><i>out_med</i> = median(<i>a</i>,0,11,11);</div> <div><i>out_rob</i> = roberts(<i>out_med</i>,0);</div> <div><i>handle1</i> = imshow('roberts',<i>out_rob</i>,1);</div>						
Remarks:							

ROTATEIMAGE							
Syntax:							
Parameters:							
Description:	Rotate image clockwise by an given angle. The background is set on Background Color						
References:							
List of used functions:							
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2007.12.3	Date of last update:	2007.12.3	Version:	2.0
History of updates:	none						
Script syntax:	<i>output</i> = rotateImage (<i>input</i> , <i>angle</i> , <i>BGColor</i>);						
Script parameters:	<i>input</i> - input image <i>output</i> - output rotated image <i>angle</i> - the angle of clockwise image rotation <i>BgColor</i> - he color of background (0 = black , 65535 = white)						
Example script:	<pre> chdir('C:\N'); % read image a = readtiff('TestSample_3.2.tif'); % show readed image handle = imshow('original',a,0); % rotate image out = rotateImage(a,6,65535); % show result handle1 = imshow('out',out,0); </pre>						
Remarks:	none						

SAUVOLA							
Syntax:							
Parameters:							
Description:	Multiprocessor implementation of Sauvola thresholding.						
References:	[1] Faisal Shafait, Daniel Keysers, Thomas M. Breuel: <i>“Efficient Implementation of Local Adaptive Thresholding Techniques Using Integral Images”</i>						
List of used functions:	none						
File name (C-code):				DLL – library name:	Sauvola2.dll		
Developed by:	PSz	Date of development:	2009.03.4	Date of last update:	2009.03.4	Version:	1.0
History of updates:	none						
Script syntax:	output = Sauvola (input, w, k);						
Script parameters:	output - image after thresholding input - image to be thresholded w - mask's size (has to be odd) k - k parameter of Sauvola thresholding – typically 0.2						
Example script:	<pre>%setting number of processors threads(2); %reading file im = readtiff('14-35-49_257A_flaw1A_normal.tif'); %thresholding A = Sauvola(org, 41, 0.2); %showing image before and after thresholding handle1 = imshow('Before', org, 1); handle2 = imshow('After', A, 1);</pre>						

SAVEFEAT							
Syntax:							
Parameters:							
Description:	Saving features in to the txt file; (new version of SEAVEFEATURES)						
References:							
List of used functions:	none						
File name (C-code):				DLL – library name:	savefeat.dll		
Developed by:	PSz	Date of development:	2007.03.20	Date of last update:	2007.09.26	Version:	1.0
History of updates:	None						
Script syntax:	svtxt(<i>tab</i> , <i>number</i> , <i>path</i>)						
Script parameters:	<i>tab</i> – table with features <i>number</i> – number of defects <i>path</i> – path with file name						
Example script:	<pre> chdir('C:\V'); % read the image original = imread('TestSample_2_3.tif'); % and display it on the screen (without scaling) handle1 = imshow('original',original,0); % median filtering med = fastmedian(original,51,51); % subtracting filtered image from original image sub = imsub(original,med); % iterative thresholding th = ith(sub,0.8); % removing small dots out_med = fastmedian(th,5,5); % recognizing flaws indexed_image = index(out_med); [num,tab] = calcfeat(original,indexed_image,out_med,30,100000); savefeat(tab,num,'wynik.txt'); im_f = genindexedimg(original,tab,num); % displaying result handle2 = imshow('ith',out_med,1); handle3 = imshow('numbered',im_f,0); </pre>						
Remarks:	-						

SAVESTAT							
Syntax:							
Parameters:							
Description:	Saves to file statistical information						
References:							
List of used functions:	none						
File name (C-code):				DLL – library name:	savestat.dll		
Developed by:	PSz	Date of development:	2007.09.20	Date of last update:	2007.09.20	Version:	1.0
History of updates:	None						
Script syntax:	savestat ('path', max, min, sred, med);						
Script parameters:	<i>path</i> - path and name of file <i>max,min,sred,med</i> - data to save						
Example script:	<pre> chdir('C:\addip\radiograms'); or = imread('TestSample_2_3.tif'); mm = dm([0,0,0,0]); img= norm_radio(or,65535,1000,2,8,mm); [max,min,sred,med]=statistic(img,mm); imwrite('result.tif',img); drukuj = imshow('result', result,0); savestat('stat1.txt',max,min,sred,med); </pre>						
Remarks:							

SAVEIMAGEM							
Syntax:							
Parameters:							
Description:	Saves image in the Matlab format. Under Matlab one has to use a special function (m-file) to import this file. The m-function is available in examples dir.						
References:							
List of used functions:	none						
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2007.03.20	Date of last update:	2007.03.20	Version:	1.0
History of updates:	none						
Script syntax:	saveimagem ('filename', image);						
Script parameters:	<i>filename</i> – file where image will be stored <i>image</i> – image to be saved						
Example script:	<pre>% read the image originalI = imread('h:\\nn\\TestSample_1_1.tif'); % saving saveimagem('c:\\output.bin', originalI); % run the following line under Matlab to import saved image % out = addipimport('c:\\output.bin')</pre>						
Remarks:							

SOBEL							
Syntax:							
Parameters:							
Description:	Sobel gradient filter.						
References:							
List of used functions:							
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2007.03.20	Date of last update:	2007.03.20	Version:	1.0
History of updates:							
Script syntax:	<i>output = sobel(input, type);</i>						
Script parameters:	<i>Input</i> - input image; <i>output</i> - output image <i>type</i> - type of mask used (0 – horizontal or 1 - vertical)						
Example script:	chdir('C:\addip\radiograms'); a = imread('TestSample_2_3.tif'); handle = imshow('original',a,0); out_med = median(a,0,11,11); out_sob = sobel (out_med,0); handle1 = imshow('sobel',out_sob,1);						
Remarks:							

STATISTIC							
Syntax:							
Parameters:							
Description:	Returns statistical data						
References:							
List of used functions:	none						
File name (C-code):				DLL – library name:	statistic.dll		
Developed by:	PSz	Date of development:	2007.09.20	Date of last update:	2007.09.20	Version:	1.0
History of updates:	None						
Script syntax:	<pre>table = dm('x1,y1,x2,y2'); [max,min,mid,med] = statistic(inpImage, table);</pre>						
Script parameters:	<i>inpImage</i> - input original image <i>table</i> - analyze region						
Example script:	<pre>chdir('C:\addip\radiograms'); img = imread('TestSample_2_3.tif'); mm = dm('0,0,0,0'); img = norm_radio(or,65535,1000,2,8,mm); [max,min,sred,med]=statistic(img,mm); imwrite('result.tif',img); drukuj = imshow('result', img,0); savestat('stat.txt',max,min,sred,med);</pre>						
Remarks:							

STH							
Syntax:							
Parameters:							
Description:	Global thresholding; operates on gray scale images The threshold is calculated for each pixel of an image using mean value of neighbours and adaptive standard deviation; output is a binary image						
References:							
List of used functions:	none						
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2007.03.20	Date of last update:	2007.03.20	Version:	1.0
History of updates:	none						
Script syntax:	<i>output = sth(input input, MaskSize, ThCoef, VarDynRange);</i>						
Script parameters:	<i>Input</i> - input image; <i>output</i> - output image <i>MaskSize</i> – size of the moving mask which contains neighborhood of selected image point <i>ThCoef</i> – threshold coefficient, that moves threshold value <i>VarDynRange</i> - dynamic range of variance						
Example script:	<pre> chdir('C:\addip\radiograms'); % using Sauvola thresholding a = imread('TestSample_2_3.tif'); handle = imshow('original',a,0); out_med = median(a,0,51,51); out_sub = imsub(a,out_med); out_ith = sth(out_sub,35,0.06,32768); out_med1 = median(out_ith,0,5,5); handle1 = imshow('sth',out_med1,1); </pre>						
Remarks:	none						

STHad							
Syntax:							
Parameters:							
Description:	Global thresholding; operates on gray scale images. The threshold is calculated for each pixel of an image using mean value of neighbours and adaptive standard deviation; output is a binary image. The dynamic range is set automatically.						
References:							
List of used functions:	none						
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2008.01.04	Date of last update:	2008.01.04	Version:	1.0
History of updates:	none						
Script syntax:	<i>output</i> = STHad(<i>input</i> , <i>MaskSize</i> , <i>ThCoef</i>);						
Script parameters:	<i>Input</i> - input image; <i>output</i> - output image <i>MaskSize</i> - size of the moving mask which contains neighborhood of selected image point <i>ThCoef</i> - threshold coefficient, that moves threshold value <i>VarDynRange</i> - dynamic range of variance						
Example script:	chdir('C:\addip\radiograms'); % using Sauvola thresholding a = imread('TestSample_2_3.tif'); handle = imshow('original',a,0); out_med = median(a,0,51,51); out_sub = imsub(a,out_med); out_ith = sth(out_sub,35,0.06); out_med1 = median(out_ith,0,5,5); handle1 = imshow('sth',out_med1,1);						
Remarks:	none						

THREADS							
Syntax:							
Parameters:							
Description:	This function initializes global variable <i>numofproc</i> . Global variables are available for all other functions.						
References:							
List of used functions:	none						
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2009.01.15	Date of last update:		Version:	1.0
History of updates:	none						
Script syntax:	<i>threads(numofproc);</i>						
Script parameters:	<i>Numofproc</i> – number of processors to use by ADDIP (only particular functions supports multi processor systems)						
Example script:	<pre> threads(2); chdir('C:\'); org=readtiff('wzorzec.tif'); bw = readtiff('wzorzec.tif'); ind = index(bw); handle3 = imshow('org',org,1); handle4 = imshow('ind',ind,1); writetiff(ind,'ind.tif',0); c = cf(org,ind,bw); % now function cf uses two processors matrixwrite(c,'features_out.m'); </pre>						
Remarks:	none						

WELDANGLE							
Syntax:							
Parameters:							
Description:	Function detect the angle of weld between a horizontal line and a maximum values line						
References:							
List of used functions:							
File name (C-code):				DLL – library name:			
Developed by:	PSz	Date of development:	2007.12.3	Date of last update:	2007.12.3	Version:	2.0
History of updates:	none						
Script syntax:	<i>output</i> = weldAngle (<i>input</i> , <i>SideWeldProfile</i>);						
Script parameters:	<i>input</i> - input image <i>output</i> - angle <i>SideWeldProfile</i> - the percent of Image resolution in x direction. The percent of weld profile at start and end of image are taken to set a maximum values line [%].						
Example script:	<pre> chdir('C:\'); %read mage a = imread('FilmFree_A_Szczecin_NA_NA_NA_TC_Spoiny_27-09-2007_14-40-04_171A.tif'); handle = imshow('original',a,1); % crop image b = cropImage(a); handle1 = imshow('cropped',b,1); % calculate weld angle of the image and rotate by this angle ang = weldAngle(b,10); c = rotateImage(b,ang,65535); handle2 = imshow('rotated',c,1); % crop image after rotation out = cropImage(c); handle3 = imshow('out',out,1); </pre>						
Remarks:	none						

WRITETIFF							
Syntax:							
Parameters:							
Description:	Writes 16-bit grayscale TIFF image.						
References:							
List of used functions:							
File name (C-code):				DLL – library name:	writetiff.dll		
Developed by:	PSz	Date of development:	2007.10.04	Date of last update:	2007.10.04	Version:	1.0
History of updates:	none						
Script syntax:	writetiff (image,'filename',normalization);						
Script parameters:	<i>input</i> - image <i>'filename'</i> - new image name <i>normalization</i> - 0 – without normalization, 1 –linear normalization to range 0-65535						
Example script:	<pre> chdir('C:\addip\radiograms'); % read image original = readtiff('TestSample_2_3.tif'); % cut part from original cut = cutroi(original,0,504,200,520); % write new image writetiff(cut,'copy.tif',0); % read new image new = readtiff('copy.tif'); % and display it on the screen (with scaling) handle1 = imshow('Original',original,1); handle2 = imshow('New',new,1); </pre>						
Remarks:	Only 16-bit images can be written using this function.						

WSKPRECLASSIFIER							
Syntax:							
Parameters:							
Description:	Works with radiograms provided by WSK. This function makes early classification for flaws and non-flaws depending on size of the object. Preliminary results are written to the text file.						
References:							
List of used functions:							
File name (C-code):				DLL – library name:	wskclassifier.dll		
Developed by:	PSz	Date of development:	2009.09.18	Date of last update:	2009.09.18	Version:	1.0
History of updates:	none						
Script syntax:	<i>preclass = wskpreclassifier(image,indexed_image,thres_image,distances,features,report);</i>						
Script parameters:	<i>image</i> – original image <i>indexed_image</i> – indexed image <i>thres_image</i> – thresholded image <i>distances</i> – distances matrix (see example) <i>features</i> – features matrix <i>report</i> – report filename <i>preclass</i> – an BW image containing only objects classified as possible flaws						
Example script:	<pre> chdir('E:\matlab\ADDIP_test\WSK'); img = readtiff('ADDIP_20090831_133241_MD3061969_op160_4_zd9_Good.tif'); imcut = cutroi(img,0,1024,600,825); out_med = fastmedian(imcut,0,31,31); out_sub = imsub(imcut,out_med); out_ith = ath(out_sub,45,1550); out_med1 = median(out_ith,0,5,5); indexed_image = index(out_med1); c = cf(imcut,indexed_image,out_med1); unused = neighb(indexed_image,40,1); distances = matrixread('c:\results.m'); preclass = wskpreclassifier(imcut,indexed_image,out_med1,distances,c,'test.txt'); indexed_preclass = index(preclass); c_preclass = cf(preclass,indexed_preclass,preclass); out = wskclassifier(preclass,indexed_preclass,c_preclass,50,'test1.txt'); handle1 = imshow('orginal',img,1); handle2 = imshow('cut',imcut,1); handle3 = imshow('med',out_med1,1); handle4 = imshow('pre_classification',preclass,1); handle5 = imshow('out_classifier',out,1); writetiff(indexed_image,'indexed.tif',1); writetiff(out_med1,'bw.tif',1); matrixwrite(c,'features_out.m'); matrixwrite(distances,'distances.m'); </pre>						
Remarks:	Due to error in neighb function, the distances matrix must be read separately from external file.						

WSKCLASSIFIER							
Syntax:							
Parameters:							
Description:	Works with radiograms provided by WSK. This function makes final classification of flaws and assigns radiogram to class A or B						
References:							
List of used functions:							
File name (C-code):				DLL – library name:	wskclassifier1.dll		
Developed by:	PSz	Date of development:	2009.09.18	Date of last update:	2009.09.18	Version:	1.0
History of updates:	none						
Script syntax:	<i>out = wskclassifier(preclass,indexed_preclass,c_preclass,inch, report);</i>						
Script parameters:	<i>preclass</i> – BW image from wskpreclassifier <i>indexed_preclass</i> – indexed image <i>c_preclass</i> – features matrix <i>inch</i> – number of pixels for inch <i>report</i> – report filename <i>out</i> – an BW with 1inch marker indicated. Negative marker stands for the B class, dotted marker rejects the radiogram						
Example script:	<pre> chdir('E:\matlab\ADDIP_test\WSK'); img = readtiff('ADDIP_20090831_133241_MD3061969_op160_4_zd9_Good.tif'); imcut = cutroi(img,0,1024,600,825); out_med = fastmedian(imcut,0,31,31); out_sub = imsub(imcut,out_med); out_ith = ath(out_sub,45,1550); out_med1 = median(out_ith,0,5,5); indexed_image = index(out_med1); c = cf(imcut,indexed_image,out_med1); unused = neighb(indexed_image,40,1); distances = matrixread('c:\results.m'); preclass = wskpreclassifier(imcut,indexed_image,out_med1,distances,c,'test.txt'); indexed_preclass = index(preclass); c_preclass = cf(preclass,indexed_preclass,preclass); out = wskclassifier(preclass,indexed_preclass,c_preclass,50,'test1.txt'); handle1 = imshow('orginal',img,1); handle2 = imshow('cut',imcut,1); handle3 = imshow('med',out_med1,1); handle4 = imshow('pre_classification',preclass,1); handle5 = imshow('out_classifier',out,1); writetiff(indexed_image,'indexed.tif',1); writetiff(out_med1,'bw.tif',1); matrixwrite(c,'features_out.m'); matrixwrite(distances,'distances.m'); </pre>						
Remarks:	Due to error in neighb function, the distances matrix must be read separately from external file.						